

NB! Dette fargebåndet krever at firmware versjon er over 1955 og driver over 6.36.0.0

Gå til ribbons.evolis.com/update
Trykk på linken til skriveren du bruker.

Latest Evolis ribbons' generation requires several updates for an optimal functioning

The updates concerns:

- Evolis Premium Suite or Edikio Printer Suite driver release 6.36.0.0 or above.
- Mac OS driver 6.8.0.174 or above.
- Firmware version 1957 or above.
- For printers that are equipped with a LCD: LCD firmware version 1955 or above

The following printers' models require this upgrade. Please follow the specific guidelines for your card printer:

- Evolis Card Printers:
 - Primacy
 - Zenius
 - Elypso
 - KC200 /KC200B
- New Kiosk range:
 - KC Essential
 - KC Prime
- Edikio Products (Guest or Price Tag):
 - Flex
 - Duplex

Her ligger det instruksjoner på hvordan man oppdaterer driver/firmware samt velger bånd manuelt i driver.

For Primacy - Zenius - Elypso - KC200/KC200B, please follow those guidelines:

A. Windows Operating System:

1a. Use the dedicated Evolis update tool to update you printer automatically

The Evolis Update Tool updates in a single operation:


- the printer's firmware
- the firmware of the LCD (only if the printer is equipped with an LCD)
- finally, the Evolis Premium Suite (a restart of the computer may be expected).

Please ensure your printer is in a ready state before to start the operation:

In case several printers are connected to the same computer, then printers are updated one by one.

Ressources


[Download Evolis update tool](#)



Standard update sequence screenshots Below (here Evolis Primacy (Copy 1) is connected, Evolis Primacy remains grey as it is not connected) :




1b. Update both driver and firmware in one operation



Ressources

- [Download Evolis Premium Suite](#)
- [Download Printer's firmware](#)

For printers equipped with an LCD:




Ressources


- [Download LCD firmware](#)

Warning: For a specific batch of ribbons (identified with a // symbol at the end of the reference on the packaging), pay attention that:

- A manual selection of the ribbons' settings is required
- Some information about those ribbons are not available : Part number and remaining capacity in the driver interface



2. Set manually the ribbon type on a Windows Operating System



Hvis dere har problemer med dette så kan dere ta ringe til 32 72 70 00 eller send e-post til support@buysec.no